

Asmus Freytag and Michael Everson**Date 2001-11-07**

The proposed EJECT SYMBOL is part of a larger set of related user interface symbols for removable and audio-visual media. The additional set consists of the following symbols.

Playback buttons

E0C3 ◀ BLACK MEDIUM LEFT-POINTING TRIANGLE
= reverse
x 25C0 ◀ black left-pointing triangle

E0C4 ▶ BLACK MEDIUM RIGHT-POINTING TRIANGLE
= forward
x 25B6 ▶ black right-pointing triangle

E0C7 ⏩ FAST FORWARD

E0C8 ⏪ FAST REVERSE

E0C9 ⏮ GO TO BEGINNING

E0CA ⏭ GO TO END

E0CB ⏸ PAUSE

E0CC ■ STOP PLAYBACK
: 25FC ■ BLACK MEDIUM SQUARE

E0CD ● MEDIUM CIRCLE
= record

EDD6 ▲ BLACK RISING RAMP
= volume

The triangles in E0CA ⏭ and E0C4 ▶ have the same size and alignment relative to the centerline of the glyph. The other symbols are sized and aligned in a similar fashion. The triangles are smaller and considerably flatter than the existing black triangles, compare 25B6 ▶ and E0C4 ▶. The STOP PLAYBACK can be unified with the existing 25FC ■ BLACK MEDIUM SQUARE.

Variation of E0C9 ⏮ and E0CA ⏭ with single triangle are very common and are used to indicate skipping a lesser distance than E0C9 ⏮ and E0CA ⏭.

Fonts often complete the set of medium triangles as follows:

E0C5 ▲ BLACK MEDIUM UP-POINTING TRIANGLE
= increase
x 25B2 ▲ black up-pointing triangle

E0C6 ▼ BLACK MEDIUM DOWN-POINTING TRIANGLE
= decrease
x 25BC ▼ black down-pointing triangle

These shapes are used in user interfaces for various indications of “up” and “down”. Unlike the BLACK TRIANGLE series, these two triangles are consistently aligned to be wholly above and below the centerline, compare 25B2 ▲ and 25BC ▼ to E0C5 ▲ and E0C6 ▼.

Notes

The code locations are private use codes assigned purely for the convenience of creating this document.